



Best Practices Rapid Deploy



Typische Scenarien

- Sichere Anbindung von Remote Standorten und Homeoffice
- Dienste werden zentral bereitgestellt
- Global verteilte Standorte
- Sicherer Austausch von Daten und Informationen
- IT Mitarbeiter sind oft nur in zentralen
 Standorten vorhanden Zentrale Administration und zentrales Reporting
- Schnelle Installation bei kleinen Kunden ohne IT Fachkraft
- Managed Service





Grundlagen

- Rapid Deploy ist ein seit langem unterstützter Mechanismus
- Viele Kunden und Partner nutzen diesen sehr intensiv und erfolgreich
- Auch nützlich als Disaster Recovery oder RMA "Unterstützung"
- 3 Varianten:
 - Management Server
 - Configuration File
 - WatchGuard Cloud



Rapid Deploy Management Server

Die patentierte Technologie ermöglicht eine schnelle und einfache Inbetriebnahme neuer Standorte. Vor Ort ist kein IT Know-How erforderlich, die Konfiguration kann zentral vorbereitet und durchgeführt werden.



Ablauf Rapid Deploy

WatchGuard RapidDeploy Process







Live Demo





Rapid Deploy Configuration File

 Eine vorbereitete Konfigurationsdatei wird im WatchGuard Account (Support Center) der Appliance zugewiesen.

Product Details for T70-JSP

Guard

	Denid Denley, Configuration
	kapidDeploy Configuration
DanidDanlay	With RapidDeploy, your device automatically downloads and applies a configuration each time it connects to the Internet with factory-default settings.
паріореріоу	🔿 Do not use RapidDeploy
Use RapidDeploy to set up autom	configuration Use RapidDeploy QuickStart
RapidDeploy is not configured.	Set up R 👩 Upload a configuration file to the website for RapidDeploy
	Make sure that your configuration file has a version that is equal to or less than the version of Fireware installed on your device.
Services & Upgrades	Durchsuchen Keine Datei ausgewählt.
Fireware® XTM Pro	Activated
Application Control	Active (Exp. Next Cancel
Gateway AntiVirus	Active (Expiration date: 28 Aug 2019) Netire mis davice Renew

Bei vielen Appliances

 Rapid Deploy Configuration Manager https://www.watchguard.com/help/docs/help-center/en-US/Content/en-US/my_products/rapiddeploy_config_mgr.html

Assign a configuration file to your app Search devices:	pliances by moving them from the left box to the right box below.
Unassigned Appliances	Assigned Appliances
D0FA02A1B-CBA3 D0FA02A36-8CA2	D0FA02EDC-5A05 D0FA02A48-7821
>	<



Rapid Deploy Configuration File

- Die Konfiguration kann bereits Parameter zur Integration in den MGMT Server enthalten.
- Das Device wird anschließend im Management Server angelegt und verbindet sich automatisch sobald das System vor Ort angeschlossen wird.

		Device: M300-Homeoffice			
		Device Information	*	Heartbeat (Alive)) 🛛 👻
		Version:	11.9.6		
		Update Status:	Complete	Tools	*
dd Device Wizard	X	Last Download:	Today 14:11:37	Policy Manager	
Entor a name for th	in davies	Serial Number:	80DF000B209C4	Firebox System Manag	ger
	Watchiduard	IP Address:	10.255.255.2	HostWatch	
		Type:	M300 running Fireware XTM	Ping	
Enter the information use	d to display the device in WSM and authenticate the device to the	Lease Time:	2 minutes	Expire Lease	
the device's Managed C Client Name: Device Type: Shared Secret:	M300-Homeoffice Fireware XTM	Configure Update Device Update License Re	boot	Device Mode Mode Settings Management Gro Member Of	Rasic Managed Mor
Confirm Shared Secret:		VPN Tunnels Name Remote Gateway	*	Settings Management Tur Type Hub Device	nnel Information 🖄 Spoke (SSL Oni XTMv-DefGa
	< Back Next > Cancel Help			Tunnel ID	SSL-M30



Erzeugen der Konfigurationsdatei

- Eine Konfigurationsdatei f
 ür die Version der Firebox kann über 2 Wege erzeugt werden
 - Per Web-UI mit "Referenz Appliance"
 - Per WSM über Option "Save as Version"

R	untitled.xml *- Fireware Policy Manager				
File	Edit View Setup Network FireCluster VPN Subs	cripti	on Services Help		
D	New Strg+N	a ,	💰 👫 🛄 🚂 🔗	E 🔍 ?	
	Open				
5	Save	H	To Firebox	Strg+T	
	Backup and Restore		As File	Strg+5	
	Upgrade	-	As Version	Strg+V	Port
	Manage Users and Roles		Always create a back	qu	tcp:21 tcp:8080
	C:\Users\jonas-admi \FBX-DefGate.xml		Any-Trusted, Any Ar	iy	icmp (type: 8,
	Exit	gmt	Any-Trusted, Any Fir Any-Trusted, Any Ar	ebox iy-External	tcp:4105 tcp:4 tcp:0 (Any) u





Live Demo



RapidDeploy über WatchGuard Cloud

RapidDeploy ist vollständig in WatchGuard Cloud integriert

- Integration neuer Standorte ohne geschultes (IT-)Personal vor Ort
- Zero-touch deployment
- Laden Sie eine vorbereitete Konfigurationsdatei in die WatchGuard Cloud die neuen Firebox Systeme wenden diese sofort an und schützen direkt.



Erzeugen der Konfigurationsdatei

- Eine Konfigurationsdatei f
 ür die Version der Firebox kann über 2 Wege erzeugt werden
 - Per Web-UI mit "Referenz Appliance"
 - Per WSM über Option "Save as Version"

5	untitled.xml *- Fireware Policy Manager					
File	Edit View Setup Network FireCluster VPN Subs New Strg+N Open >>	ariptic	on Services Help 🎉 👫 🖳 🚂 🔗	E 🔍 ?		
5	Save	-	To Firebox	Strg+T		
	Backup and Restore	-	As File	Strg+5		
	Upgrade	-	As Version	Strg+∀	Port	
	Manage Users and Roles		Always create a backu	qı	tcp:21 tcp:8080	
	C:\Users\jonas-admi \FBX-DefGate.xml	1	Any-Trusted, Any An	y	icmp (type: 8,	
	Exit	gmt .	Any-Trusted, Any Fin Any-Trusted, Any An	ebox y-External	tcp:4105 tcp:4 tcp:0 (Any) u	



Copyright ©2019 WatchGuard Technologies, Inc. All Rights Reserved

Kling gut! Aber was passiert ohne DHCP?

- IP address type
 - Static
 - PPPoE
- IP information can be configured in .csv file on USB Stick 70XX00777X777,0,ext,Static,69.164.168.168/24,69.164.168.254,202.106.0.20 ANNALSA ANNALSA
 - 1

Format is documented:
https://www.watchguard.com/help/docs/help-center/en-US/Content/en-
US/Fireware/deploy/usb_interface_config_c.html

Multiple serial numbers for	1
Multiple Serial Humbers for	serial
multiple locations	8083

A	B	C	D	E	F	G
serial no	intf#	intf type	public IP type	ip	gateway	dns
80B302ABA2AB9	0	ext	Static	67.79.167.94/24	67.79.167.1	4.2.2.2
				1.000		
	-					





Neu in Version 12.5.3

 Neuer Web Setup Wizard mit Rapid Deploy Option

 WLAN eingeschaltet im Factory Default



Cont Fireware Web UI Specify address Cont Fireware Web UI © Obt Specify Fireware Web UI © Obt Specify Connection Settings: PPPoE IP Addr Specify the PPPoE settings to use for interface 0. Gatewa © Obtain an IP address automatically © Use this IP address Use this IP address	WatchGua	rd Fireware Web UI
Specify DHCP1 Conr Fireware Web UI Image: Specify Use Specify Connection Settings: PPPoE Image: IP Addr Gatewa Specify the PPPoE settings to use for interface 0. Lease 1 	Coni 🕑	Fireware Web UI
Specify Connection Settings: PPPoE Use IP Addr Gatewa Specify the PPPoE settings to use for interface 0. Lease 1 Image: Obtain an IP address automatically Client Use this IP address Host N User Name	Specify DHCP JI CO	nr WatchGuard Fireware Web UI
	Obt Obt Use IP Ai Gate Client Host N	cify Connection Settings: PPPoE ddr Specify the PPPoE settings to use for interface 0. © Obtain an IP address automatically © Use this IP address





Vielen Dank!

